



**Standard
Evaluator's Guide**



©2021 Software Pursuits, Inc.

Table of Contents

| | |
|--|----|
| Introduction | 2 |
| System Requirements | 2 |
| Contact Information | 3 |
| SureSync Add-On Licenses | 4 |
| Communications Agent Add-On..... | 4 |
| File Locking Add-On..... | 4 |
| ArchiveSync Add-On..... | 5 |
| Our Scenario..... | 5 |
| Installation..... | 6 |
| Launch SureSync for the First Time | 7 |
| Creating a SureSync Database..... | 7 |
| Configuring the Local Communications Agent..... | 9 |
| Importing a License | 11 |
| Installing the SureSync Scheduler..... | 11 |
| Creating the Job | 13 |
| Name Your Job | 14 |
| Specifying Root Paths..... | 14 |
| Determining the Best Rule | 18 |
| Selecting Your Rule & Defining Folder Exclusions | 18 |
| Selecting the Source Path..... | 20 |
| Filtering Based on File Masks | 20 |
| Previewing Your Job | 21 |
| Creating a Schedule | 22 |
| Name Your Schedule | 22 |
| Selecting What Job(s) to Run | 22 |
| Configure Scheduling Options | 24 |
| Modifying and Running Your Schedule..... | 25 |
| Configuring E-mail Alerts..... | 25 |
| Configuring a SMTP Profile..... | 25 |
| Configuring an Alert Profile | 27 |
| Configuring the Schedule to Send Alerts | 28 |
| Monitoring the Synchronization | 30 |
| Detailed Status | 30 |
| Enterprise Status..... | 31 |

Introduction

SureSync is a powerful file replication & synchronization application that can be used to ensure users on your network are always working off of the most recent version of critical files, for disaster recovery purposes, software distribution, and much more.

This evaluator's guide is designed to walk you through the initial setup of the SureSync product. The base SureSync product can perform one-way and multi-way synchronizations via UNC path or drive mapping. These synchronizations can be run manually or on a scheduled basis. By reviewing this guide, you will become familiar with how to use SureSync to implement an efficient and powerful synchronization / replication infrastructure in your network.

System Requirements

SureSync's basic operating system and hardware requirements are:

- **Supported Operating Systems:** Windows Server 2022; Windows Server 2019; Windows Server 2016; Windows Server 2012 R2; Windows Server 2012; Windows Server 2008 R2 with SP1; Windows Server 2008 with SP2; Windows 10; Windows 8.1; Windows 8; Windows 7; Windows Vista with SP2
- **Processor:** Minimum: 1Ghz (x86 processor) or 1.4Ghz (x64 processor). Recommended: 2Ghz or faster processor (x86 or x64 processor)
- **RAM (total for system):** 1GB (Minimum); 2GB (Recommended)
- **Hard Disk:** 30MB for application files; 20MB+ for database
- **Display:** 1024x768 high color, 32-bit (Minimum)

SureSync is a 32-bit application but will run on 64-bit versions of Windows. 64-bit editions of Windows include full featured emulation for running 32-bit code that allows SureSync to run on these operating systems. The File Locking Add-on is 64-bit compatible.

SureSync can synchronize data to operating systems such as Windows 2000, and non-Windows machines such as Macintosh and Linux machines via UNC path but the software itself must be installed on one of the supported operating systems listed above.

Windows 2003/XP Support – Communications Agent Only

Windows 2003 and Windows XP are no longer supported by Microsoft. User interface components such as the SureSync Desktop, status panels, SyncLockStatus and Endpoint require the .NET Framework 4.5.2. This version of the .NET Framework is not available for these operating systems. Machines running any of these components must be upgraded to a supported operating system.

A version of the Communications Agent running the .NET Framework 4.0 will be installed automatically on Windows 2003 with SP2, Windows 2003 R2, and Windows XP with SP2 machines. This allows you to synchronize files to paths on these operating systems using Communications Agent functionality. You can also synchronize to them via UNC path.

Virtualization

SureSync can be run on Windows operating systems hosted in virtualization software such as VMWare or Hyper-V without issue. Each virtual machine involved in the synchronization / replication requires appropriate licensing.

SureSync Database Requirements

SureSync requires a database to store configuration information. The following formats are supported:

- Microsoft Access (default)
- SQL Express 2005, 2008, 2012, 2014, 2016, 2017 and 2019
- SQL Server 2005, 2008, 2012, 2014, 2016, 2017 and 2019

While SureSync will operate with older versions of SQL Server, it is strongly recommended to use the newest possible release to take advantage of performance and reliability enhancements in those versions of SQL Server.

To achieve optimal performance, SQL database is strongly recommended for setups using multi-directional rule types, environments with more than 50 Relations defined, or environments where hundreds of thousands of files will be processed.

SureSync requires a number of Microsoft components to be installed on the system. The SureSync installer will inspect your system for these components and offer to upgrade or install them as needed.

- Microsoft .NET Framework 4.5.2
- Microsoft .NET Framework 4.0 (Windows 2003/XP)
- Microsoft MDAC 2.8 Refresh with Service Pack 1
- Microsoft Visual C++ Runtime 14.0 (Visual Studio 2015)
- Microsoft Windows Installer 3.1
- Microsoft XML Parser 6.0
- Microsoft Jet 4.0 with Service Pack 8

Please note that using the SureSync installer to install these prerequisites could result in a reboot being necessary before the setup can continue. If a reboot is necessary, the installer will prompt you. In environments where a reboot is disruptive, we recommend installing the required components manually during your normal maintenance schedules and then proceeding to install SureSync.

Contact Information

If you need further information about SureSync or need clarification on anything within this guide, please contact our support group and they will be happy to assist you with your evaluation.

Software Pursuits, Inc.
951 Mariners Island Blvd, Ste 300
San Mateo, CA 94404

Phone: +1-650-372-0900
Fax: +1-650-372-2912

Sales e-mail: sales@softwarepursuits.com
Support e-mail: support@softwarepursuits.com

Technical support is available between 7:00AM and 4:00PM PST Monday through Friday.

SureSync Add-On Licenses

A number of Add-On licenses are available for SureSync that enhance the capabilities and performance of the software. The available Add-On licenses include:

Communications Agent Add-On

Ensure high availability and improved replication performance with SureSync's Communications Agent Add-On. The Communications Agent provides technology to perform real-time synchronization/replication and more. Below is a list of features that are included when you license the Communications Agent Add-On.

- **Real-Time Monitors**
Real-Time processing increases data availability by continuously monitoring data for updates. By processing files immediately after they change, SureSync can avoid folder scans that are necessary for scheduled jobs.
- **Remote Differential Compression (RDC)**
RDC copies only the changes made to a file, reducing synchronization time and decreasing the consumption of network resources.
 - **RDC to Non-Windows Machines**
If you map a non-Windows drive to a drive letter on a Windows machine you can process delta copies to that non-Windows machine. This in turn provides bandwidth savings between any machines, regardless of the OS.
- **File Compression**
Transmit files in a smaller package across your network by compressing them. File compression is particularly useful on slow network connections.
- **TCP/IP Transmissions**
Transmissions across the Internet give you more options on how you connect to remote machines. Now it is even easier to keep office branches connected to the information they need.
- **Encryption**
Ensure your files are being transmitted securely by encrypting each file transmission. Multiple FIPS certified encryption algorithms are available. This is an especially useful and necessary option when transmitting sensitive data across the Internet.
- **Change Journal Support for Schedules**
When a Schedule is configured to run a Job using the Communications Agent Add-On, SureSync uses the NTFS Change Journal to minimize the amount of scanning performed. Eliminating much of the scanning creates a significant performance improvement for Schedules.

Please consult the [SureSync Pro Bundle Evaluator's Guide](#) for further details.

File Locking Add-On

The File Locking Add-On requires the Communications Agent to be licensed and gives you an additional benefit in collaborative file sharing environments. The File Locking Add-On eliminates the possibility that a file could be changed on multiple sides of a synchronization resulting in a more efficient synchronization with zero risk of lost changes. A user who attempts to open a file that is already in use will receive an indication from the application that the file is locked.

Please consult the [SureSync Collaboration Bundle Evaluator's Guide](#) for further details.

ArchiveSync Add-On

SureSync's ArchiveSync Add-On allows users to create versioned backup copies of files, providing an efficient disk-to-disk backup solution. Versioned file copies allow users to quickly restore files to a specified point-in-time, without sifting through tape backups. Additionally, when archiving or restoring, the ArchiveSync Add-On will allow you to backup and restore security privileges.

Archiving can be done in real-time to continuously protect data, effectively eliminating tight backup windows during the evening. ArchiveSync will also automatically thin out your archive to clean storage up.

Please consult the [SureSync with ArchiveSync Add-On Evaluator's Guide](#) for further details.


Our Scenario

This guide will walk you through the configuration of SureSync to accomplish a one-way distribution of files from a source server named *DEV20* to two destination servers named *SPITest-Win2K8* and *SPITest-Win2K12*.

In this scenario, SureSync will be used to mirror data from a staging server to two destination production machines. This is a common scenario for tasks such as web site publishing, updating templates or distributing application updates.

In this example, a folder C:\Web will be mirrored from *DEV13* to the [\\SPITestWin2K8\Web](#) and [\\SPITestWin2K12\Web](#) shares on a scheduled basis.


This guide will show you how to configure a one-way synchronization job using a Schedule run on a clock basis. In this example, the Schedule will run once an hour. SureSync also has the capability to run in real-time. When run in this mode, changes are synchronized as they occur. This functionality requires the Communications Agent Add-On license. Please consult the [SureSync Pro Bundle Add-On Evaluator's Guide](#) for further details about configuring a Real-Time scenario.




Installation

To begin your SureSync trial, you must install the correct SureSync components on the right machines. SureSync is installed using a Windows Installer installer. SureSync and all Add-On products are installed using the same installer.

For this scenario, the full SureSync application will be installed on one machine (*DEV20*). No software needs to be installed on the remote machines when performing a UNC or drive mapping based synchronization/replication.



On the *DEV20* machine, we will run *SureSyncSetup.exe* and select *SureSync* as the installation type in the installer. This will install the complete *SureSync* application and designate *DEV20* as the machine where we configure and run our synchronization.




Launch SureSync for the First Time

Now that the required components have been installed, we can continue with the configuration. To launch *SureSync* for the first time, go to the Start menu, select the *SureSync* folder and click on the *SureSync Desktop* icon. This will launch the *SureSync Desktop* where you will perform your entire synchronization job configuration.

On the first launch of the application, *SureSync* will present you with a series of questions to aide in completing the initial configuration.


Creating a SureSync Database

The prompt displayed below informs you that a *SureSync* database needs to be created. The *SureSync* database is used to store all of your synchronization/replication configuration and related information. This database can be either an Access or SQL database.




Click "OK" to continue on with the creation of the database.


The next dialog box allows you to select an existing SureSync database to open with the new installation or allows the creation of a new database. For our example, this is a new installation and “Yes” should be selected to create a new database.



On the next panel, the type of database is selected. For our example, we will select “Create a new Access/Jet database”.




The form will change to show the path to the Access/Jet Database. We will select the default location of C:\Users\Public\Software Pursuits\SureSync8\SureSync.mdb.



Configuring the Local Communications Agent


The next step in the initial configuration involves defining a credential for the local Communications Agent to run under.




Click "OK" and the Communications Agent Configuration panel will be launched.

The local Communications Agent must be given a credential for SureSync to function properly. We recommend this account be either a local administrator on the machine or a domain administrator to ensure rights to all the files and folders being synchronized. The local Communications Agent must be configured even if you're not licensed for the Communications Agent Add-on. The Add-on functionality is enabled by a license but the Communications Agent on the SureSync machine is responsible for all the basic I/O as well.

The only exception to the need to configure the local agent is if no paths of any kind, including UNC paths are referenced from the local machine. This scenario is extremely rare.



When the "Create Computer Configuration" wizard loads, the name of the computer SureSync is installed on is automatically filled in. For this example, the machine name is DEV20. Click "Next" to continue.



The “Computer Information” panel of the wizard is where you define the user account and password that the Communications Agent should use to access the files on the machine.

To ease initial configuration, the “Run a Communications Agent on this machine” option will be checked. In addition, the account you are logged into the machine as will be prefilled in the “Login Name” field.

If you want the Communications Agent to run under a different user account, you can change it here. The account must be in domain\user or machinename\user format.


Enter the password for the defined account twice in the password fields.

When a Communications Agent configuration is saved, a default connection for TCP port 9032 is created automatically. In most environments, only the default connection is used.

To test the connection, click the “Test Connections to Agent” button.

Click “Finish” to complete Communications Agent configuration for the local agent.

The following dialog will appear, click “OK to proceed to the SureSync Desktop.




Importing a License

A license file should be installed in the new database. This can be a trial license obtained from the Software Pursuits sales team or purchased license.

If you are new to SureSync, you should request a trial license from <http://www.softwarepursuits.com/suresync/standard/trial/>. A license file will be generated and sent to you via e-mail. You can also call our sales team at 1-800-367-4823.




Once a license file has been provided to you, click the “Licenses” button () in the ribbon bar of the SureSync Desktop and click the “Import License...” button to import the updated file.


Installing the SureSync Scheduler

The SureSync Scheduler is a Windows service that runs on the main SureSync machine. This service is responsible for launching Schedules at the correct times and for running Real-Time Monitors. You must have a Scheduler running in order for your Schedule to execute at the configured time.

To install the SureSync Scheduler service, click on the Home button in the upper left hand corner of the SureSync Desktop and click on “Scheduler Services.”




To install the Scheduler, click the “Install” button, which will launch a window like the one below.




The user account the Scheduler service runs under must be a member of the local administrators group on the SureSync machine. If using SQL, the account must also be a DBOwner on the SureSync database.

Enter the username formatted as *machinename\username* or *domainname\username*. This account must be an administrator on the machine. Click "Save" to install the service.


You will receive a confirmation dialog box that the Scheduler service was installed successfully as shown below.



The Scheduler will appear in the dialog with a status of (Stopped).



Once the service has been installed, click on the machine name and click “Start.” The Scheduler will now be listed as Machine Name (Running).




Creating the Job


Jobs are the basic building blocks of SureSync. Each Job contains the root paths (source and destination paths) that apply to that Job and options for the Job. Each Job also contains one or more Rules that tell SureSync how to replicate & synchronize data. The Job and the Rule are created together in one wizard.

The wizards are designed to quickly and easily configure the basic options needed to get a Job up and running. SureSync is an extremely flexible product with many advanced options. Additional options can be specified on the properties panels for the Job after it has been created.



Click on the Job button () in the ribbon bar to launch the Job Wizard. The Job Wizard will be used to configure your synchronization / replication.

Name Your Job




The first panel in the wizard allows you to name your Job. Enter the name of the Job and an optional description and click “Next” to continue. The Job name used for this example will be “Publish Web Data.”

Specifying Root Paths

The next panel is used to specify the source and destination root paths that you want to synchronize. Later in the wizard you will specify the source path for the one-way Rule we are creating. In this dialog box, you are simply listing the source and destination paths that will be part of this synchronization.

If you do not define at least two root paths on this panel, the only Rule methods available later in the wizard will be “Delete” and “Skip.”




Root paths are added by clicking the “Add” button at the bottom of the panel.


For this example, our root paths are:

- C:\Web on DEV13
- [\\SPITEST-WIN2K3\Web](#) on SPITEST-WIN2K8
- [\\SPITEST-WIN2K8\Web](#) on SPITEST-WIN2K12

First, we will select the local path on DEV13 by browsing to that path through “My Computer,” highlighting the directory and clicking “OK.”




Once that path has been added, we must add the paths on the remote machines. Click the “Add” button again to add a new path. Then you can browse through “Network” to the remote machine and select the share, select the drive letter if using a drive mapping, or manually type the path into the “Root Folder” field. In this case, we have used the browse panel to select the UNC path.




If you select a drive mapping, the path will be converted to a UNC path. Drive mappings are specific to a user so if you execute a Schedule automatically via the Scheduler service and are not logged in a drive mapping would fail. A UNC path points to the same resource but is always available.

By default, SureSync will access UNC paths using the credential defined earlier for the Communications Agent. In some cases, this credential will not be valid on the remote UNC path. For example, if you’re on a workstation running as a local account and trying to access a resource on a domain or a non-Windows machine.


In these cases, you must define a specific credential for the UNC path to use. This is done by clicking on the Options tab and clicking on the “Change...” button for the “User Id for UNC path access” option as displayed below.



In the dialog box that appears, enter a correct user ID and password for accessing the UNC path in question and then click the “OK” button.



Click “Save” to add the path. Continue clicking “New” and adding paths until all the paths involved in the synchronization are present.



Once all of the paths have been entered, press the “Next” button to continue.

Determining the Best Rule


SureSync offers a number of different replication & synchronization methods, allowing a great deal of flexibility in how your data is handled. A chart detailing each of these Rules can be found in the help file under “Rule Methods Summary.”

Selecting Your Rule & Defining Folder Exclusions


On this next panel we will specify the Rule to use for this job.

If the panel indicates that only the "Delete" and "Skip" Rules are available, you have selected only one root path. To correct the problem, you should click the "Back" button on the wizard and add the additional path(s) that will be processed by the Job.

The type of Rule we will be using in this example is “Mirror.” The panel will load looking like the screenshot below.



To select the Rule type, pull down the “Rule Type” drop-down and select “Mirror.”



The “This rule applies to the following subfolders” section of the panel allows you to include or exclude specific subfolders. The default “\” means to include all subfolders. You can enter subfolders into the text field or select them using the checkboxes in the browse dialog on the lower portion of the wizard panel. Folders are excluded by placing a minus character (-) in front of the folder name. Multiple folder entries are separated by the vertical bar character (|).

Examples

To synchronize only two subfolders named “FolderA” and “FolderB,” you would enter the following:

\FolderA\ | \FolderB\

To synchronize all subdirectories except for subfolders “FolderA” and “FolderB,” you would enter the following:

\ | -\FolderA\ | -\FolderB\

For our example scenario, the default “\” option will be used to process all subfolders.


To learn more about how to include and exclude subfolders, press the “F1” key on this panel.

Click the “Next” button to continue.

Selecting the Source Path

The next panel is where you indicate the source root path. This is done by selecting the path from the drop-down menu. All other paths are configured as destinations. In this example, the source path is the C:\Web folder on DEV13.

Your wizard panel should look like:




Click the “Next” button to continue.

Filtering Based on File Masks

The next panel displayed will let you indicate the files to be included or excluded from the synchronization. Each entry in this panel should be separated by a vertical bar (|) character. To exclude a file name or file type, place a minus sign (-) in front of the mask.

The default file mask is *.* which includes all files. Some common exclusions you could consider adding are: *.tmp | ~*.doc | ~\$.doc? | ~\$.xls?. This excludes tmp files and some Microsoft Office temporary files.



Examples

To synchronize only *.doc files and a file named "Test.txt," you would enter the following:

```
*.doc | Test.txt
```

To exclude *.tmp files, *.doc files, and a file named "Test.txt," you would enter the following:

```
*.* | -*.tmp | -*.doc | -Test.txt
```

To learn more about how to include and exclude files based on file masks, press the "F1" key on this panel.

Clicking the "Finish" button will create your Job. The Job Wizard only displays a subset of essential options for a Job. There are many other options that can be configured by modifying the properties of the Job using the SureSync Desktop. Pressing the "F1" key on any tab in the application will display context sensitive help detailing the options on that tab.

Previewing Your Job


SureSync provides two methods to preview the actions that will be performed by a Job. The first option is the Preview that provides a graphical user interface display of all actions that would be performed without actually doing them. To launch a Preview, click on the Job in the SureSync Desktop and click on the Preview button in the Ribbon Bar. Further details about Preview are available in the SureSync help file.

The second option is called a Trial Run. This method produces a tab delimited file containing the actions that would be performed. This file can easily be opened in Microsoft Excel to be viewed. To run a Trial Run, right click on the Job and select "Trial Run." Further details about Trial Run are available in the SureSync help file.

Creating a Schedule

A Schedule is used to run a Job or set of Jobs on a clock/calendar basis. For example, you could run the Schedule once every hour, once a day, or once a week.

A Job can only be active once at a given time. If you're planning to run a Job using a Schedule you should not attempt to run the same Job with a Real-Time Monitor. If you already are running a Job in a Real-Time Monitor it cannot be run in a Schedule until the Real-Time Monitor is stopped.



To create a Schedule to run your Job automatically click on the “Create Schedule” button (Schedule) on the ribbon bar. This will launch the appropriate wizard.

The wizards are designed to quickly and easily configure the basic options needed to get a Schedule up and running. SureSync is an extremely flexible product with many advanced options. Additional options can be specified on the properties panels for the Schedule after it has been created.


Name Your Schedule

A screenshot of a software dialog box titled "Create New Schedule". The dialog has a light blue border and standard window controls (minimize, maximize, close) in the top right. The main content area is white and contains the following elements: a label "Schedule Name" above a text input field containing "Schedule Web Data"; a label "Description" above a larger, empty text area; a status line indicating "Next execution scheduled for 1/1/1900 12:00 AM"; and a checked checkbox labeled "Hold Schedule". At the bottom right, there are three buttons: "Cancel", "< Back", and "Next >".

The first panel allows you to name your Schedule. Enter the name of the Schedule and an optional description. Then click “Next” to continue.


Selecting What Job(s) to Run

The next panel is where you specify the Job(s) you would like this Schedule to run. Jobs are selected by performing a drag and drop operation from the “Available Jobs” column to the “Selected Jobs” column.



Multiple Jobs can be run under one Schedule. To do so, add all the Jobs you want this Schedule to run under the “Selected Jobs” column. The Jobs will be run in the order listed. To modify the order of execution simply click on one of the Jobs and drag it up or down the list to change the order.


For our example, drag and drop the “Publish Web Data” Job into the “Selected Jobs” column. The panel should now look like this:



Click the “Next” button to continue.

Configure Scheduling Options

The next panel of the wizard determines the scheduling options for the Schedule.




From this panel, you can configure a Schedule to be run once, run every day, or run on selected days.

For our example, we want the Schedule to run every day of the week and execute once an hour.

To do so, select "Run Schedule every day." This option tells the Schedule to execute once a day every day. You can also configure a start date and time using the "Date to start running" and "Time to start running" options. For this example, we will leave those at default.

To configure the Schedule to run multiple times in a single day, like the once an hour we desire for this example, you should check "Run Multiple Times Each Day." For the "Time between each execution (hours:minutes)" option enter "01:00." This configures the Schedule to run once every hour.

The completed panel should look like this:



Click the “Finish” button to create the Schedule with the selected settings.

Modifying and Running Your Schedule

When the wizard is complete you will be returned to the SureSync Desktop and the Schedule you created will be displayed.

You can make changes to the options for your Schedule in the main SureSync window by first clicking on the Schedule you wish to modify. You can then look through the tabs on the right side for options to change. Pressing “F1” while on any tab will bring up context sensitive help describing the options in detail.

The Schedule will automatically run at the time you selected during the wizard.

Configuring E-mail Alerts


E-mail alerts are part of the Alert system within SureSync and can be a useful way of notifying the SureSync administrator of a problem that should be investigated.

Configuring a SMTP Profile



To start the configuration of e-mail alerts, you should click on the Options (Options) button in the Ribbon bar. Click on the “Alerts” tab to access the appropriate configuration panel.

The first item configured is the SMTP Profile. The SMTP Profile provides SureSync with the necessary details about your SMTP e-mail server so the program can send e-mail messages to you.



To create a SMTP Profile, click on the “New” button on the SMTP Profiles tab.


The following fields must be configured:

- **Profile Name:** The name of the profile that you are configuring. For example, you might use the name of the SMTP server.
- **SMTP Server:** The server address of the SMTP server. For example, smtp.mail.com.
- **Port:** The SMTP port for the SMTP server. The default SMTP port is 25.
- **Use TLS Encryption:** If your SMTP server requires encryption, check this box.
- **Sender Name:** The name that will appear in the From: field of messages sent by SureSync.
- **Sender Address:** The e-mail address that will appear on messages sent by SureSync.
- **Reply Address:** The reply address that will appear on messages sent by SureSync.

You can also define SMTP Server Authentication settings if your SMTP server requires a valid logon to send messages (most do). To define a credential, click the ‘Click to set the SMTP server credentials’ button. The following fields will be presented:


- **User Name:** The username that SureSync will log into this SMTP server with when sending an e-mail alert.
- **Password:** The password for the username defined in "User Name" should be entered here.
- **Repeat Password:** The password for the username defined in "User Name" should be confirmed here.

Click “Apply” to save the SMTP Profile.



Configuring an Alert Profile

The second part of configuring E-mail Alerts is to define an Alert Profile. The Alert Profile defines the e-mail address(s) that will be sent messages when errors occur. To configure an Alert Profile, click on the Alert Profiles tab and click the “New” button.



The following fields need to be configured:

- **Profile Name:** The name of the profile.
- **Recipient Address(es):** The e-mail address(es) that SureSync will send the alert messages to.
- **SMTP Profile:** The SMTP profile that will be used to send the message.

Multiple e-mail addresses can be added by separating the addresses with commas (,) or semi-colons (;). This allows you to easily send messages to a group of SureSync administrators.


Configuring the Schedule to Send Alerts

The final step for receiving e-mail alerts from the Schedule is to define an Alert Filter on the Schedule.

A global Alert Filter can be defined on the Alerts tab of Options. These global Alert Filter settings are inherited by all Jobs, Schedules and Real-Time Monitors defined in the database. Global Alert Filters can be overwritten for a specific Job, Schedule or Real-Time Monitor as appropriate.


You can also define an Alert Filter on a specific Job, Schedule or Real-Time Monitor. This is what will be done in this guide.

Click on the “Schedule Web Data” Schedule and click on the “Alert Filters” tab.




The screenshot shows a software interface for configuring alert filters. At the top, there is a 'Schedule' dropdown menu set to 'Schedule Web Data'. Below this is a horizontal tab bar with the following tabs: 'General', 'Options', 'Jobs', 'Scheduling', 'Scripts', 'Logging', 'Alert Filters' (which is selected), and 'Security'. The main content area contains the instruction: 'Click the New Alert Filter button to create a new filter.' Below this instruction is a table with two columns: 'Alert Name' and 'Address', both with a downward arrow indicating a dropdown menu. The table is currently empty. At the bottom of the table area are two buttons: 'New Alert Filter' and 'Delete Filters'. At the very bottom of the window are three buttons: 'View Errors', 'Cancel', and 'Apply'.

Click on the “New Alert Filter” button.




From the drop-down menu on the “Select Alert Profile” panel select the Alert Profile you want to configure. Click “Next” to continue.



On the next panel, you can define the types of alerts you would like to receive via e-mail. For a full description of all available options, press F1 to launch the context sensitive help.

Click “Finish” to create the Alert Filter. It will be displayed in the Schedule properties.



Monitoring the Synchronization


Monitoring your synchronization job is important, and SureSync makes this process easy through the use of two different status panels.


Detailed Status

The detailed status panel will show you file level activity for a current job as well as common counters such as files added and files deleted. If you want to take an in-depth look at a particular job, you will want to use Detailed Status.

To launch Detailed Status, right click on the job and select “Job Status.”



You can also select the job and click on the “Status” button () in the Ribbon Bar.



Enterprise Status

The Enterprise Status panel can be used to view the current status of jobs from SureSync installations anywhere on your network. The Enterprise Status panel provides an easy way to stay current on the status of your jobs, no matter where they are running.

Enterprise Status can be launched by going to the Start menu, selecting SureSync 8 and then “SureSync 8 Enterprise Status.”



You can also click on the “Ent Status” button (Ent Status) in the Ribbon Bar.

